## HTTP request



HTTP request is a default Switch app that for each incoming job executes an HTTP or HTTPS request. Thus the incoming job is a request trigger and it can be used to define the request specification: URL, authentication data, request parameters, file to upload, etc. The protocol type (HTTP or HTTPS) is automatically detected from the URL: if the URL starts with "https://", HTTPS is used, otherwise HTTP is used.

The server responds to the request by sending something back: an HTML source, JSON or XML data, or a file that is downloaded. The tool provides properties to manipulate this server response. The server response is always saved as a file and the tool can inject this file into the flow as a new job, attach it as metadata dataset to the incoming job or assemble it into a job folder together with the incoming job.

## Keywords

If you enter one of the following keywords in the Search field at the top of the Flow Elements pane, the **HTTP request** element will be shown in the list:

- HTTP
- HTTPS
- POST
- PUT
- GET
- HEAD
- DELETEdownload
- upload
- request

## **Connections**

HTTP request supports outgoing traffic light connections:

- The 'Data' connections transfer the server response file as well as the input job (depending on the property values specified for the flow element).
- The 'Log' connections transfer a generated text log file containing the request URL, the finished status, the status code, the status description, the last error and other relevant information. The log file name is generated from the input job file name by replacing the input job extension with 'log'.
- The 'Success out' connections are used in case the request finished status is 'Ok' and the HTTP request status code is in the range 100-299.

• The 'Error out' connections are used in case the request finished status is not 'Ok' or the HTTP request status code is in the range 300-599. The input job may fail in case of some internal tool error or invalid tool settings.

## **Properties**

Property	Description
Element type	The flow element type: HTTP request.
	This property is useful to identify renamed flow elements. It cannot be changed.
Name	The name of the flow element displayed in the canvas.
Description	A description of the flow element displayed in the canvas. This description is also shown in the tooltip that appears when moving your cursor over the flow element.
URL	The URL to fetch. The URL string must be URI-encoded (in a URI-encoded string a space is shown as %20).
	The tool detects the protocol to use for the request automatically from the URL: if the URL starts with 'https://', the tool will use HTTPS, otherwise HTTP will be used.
	<b>Example 1</b> (entered using the 'Single-line text with variables' editor); assumes the job name can contain only ASCII alphabetic characters and digits:
	https://api-content.dropbox.com/1/files_put/auto/ [Job.Name]
	<b>Example 2</b> (entered using the 'Script expression' editor):
	HTTP.encodeURI( "https://api-content.dropbox.com/1/ files_put/auto/" + job.getName() );
Request type	The type of the request.
	The supported request types are:
	<ul> <li>HEAD (used for retrieving response headers)</li> <li>GET (used for downloading data)</li> <li>PUT (used for uploading data)</li> <li>PATCH (used for modifying data)</li> <li>POST (used for uploading with extra parameters)</li> <li>POST a body (used for uploading, with the option to</li> </ul>
	<ul> <li>POST a body (used for uploading, with the option to define the source of the content of the body of the POST request).</li> <li>DELETE (used for removing resources on external services)</li> </ul>
	Note: Some request types define a default value for the "Content-Type" header in the request, e.g. when using POST/POST a body, the default is application/octet-stream. It's therefore

Property	Description
	recommended to define the correct Content-Type header in the Headers property (see below).
Attached file	This property is available only if <b>Request type</b> is <i>POST</i> or <i>PUT</i> .
	A file to append to request if the POST or PUT requests are used. The file will be uploaded to the server.
Use MIME encoding	This property is available only if <b>Request type</b> is <i>POST</i> .
	To use MIME encoding, choose <b>Yes</b> ; otherwise choose <b>No</b> (default).
File variable	This property is available only if <b>Request type</b> is <i>POST</i> and <b>Use MIME encoding</b> is <i>Yes</i> .
	The name of the HTTP form data variable that is used by the receiving HTTP server to identify the correct file part of the uploaded MIME package.
Body content	This property is available only if <b>Request type</b> is <i>POST a body</i> .
	The content of the body of the POST request.
	Options are:
	<ul> <li>Input job: The body of the POST will be the contents of the input job.</li> </ul>
	Dataset: The body of the POST will be the contents of the dataset. The dataset name has to be specified in the subordinate property.
	<ul> <li>Custom: The body of the POST will be the contents of the text defined in the subordinate property. You can generate a multi-line text with variables to structure a JSON file, an XML, or a similar format that is needed by the server for the POST request body.</li> </ul>
Authentication scheme	The authentication scheme to use when server authorization is required:
	None (default): No authentication is performed.
	Basic: Basic authentication based on a user name and password.
	Digest: Digest authentication (requires a user name and password).
	NTLM: NTLM authentication (requires a user name and password).

Property	Description
	OAuth: OAuth ("Open Authorization") authentication. The authorization string must be supplied through the Authorization property.
	OAuth 2.0: OAuth 2.0 ("Open Authorization 2.0")     authentication. The authorization string must be supplied through the OAuth 2.0 authorization property.
User name	This property is available only if <b>Authentication scheme</b> is <i>Basic</i> , <i>Digest</i> or <i>NTLM</i> .
	A user name if authentication is to be used.
Password	This property is available only if <b>Authentication scheme</b> is <i>Basic</i> , <i>Digest</i> or <i>NTLM</i> .
	A password if authentication is to be used.
Authorization	This property is available only if <b>Authentication scheme</b> is <i>OAuth</i> .
	The authorization string to be sent to the server.
OAuth2.0 Authorization	This property is available only if <b>Authentication scheme</b> is <i>OAuth2.0</i> .
	The authorization string to be sent to the server. Click the three dots to open the dialog to enter the parameters necessary to initiate the OAuth2.0 authorization:
	<ul><li>Application ID</li><li>Application password</li></ul>
	<ul><li>Redirection port (or select the 'Automatic' checkbox)</li><li>Authorization URL</li></ul>
	<ul><li>Token URL</li><li>Scope</li></ul>
Parameters	The parameters to attach to the request. Each parameter should be specified in a separate line by the string 'key=value' (without quotes).
	The parameters are URI-encoded automatically. For the POST and PUT requests, the parameters are included in the HTTP request after the HTTP headers. For the HEAD and GET requests, the parameters are appended to the URL after the question mark ('?').
	Example:
	root=auto
	path=[Job.JobState]
Headers	The headers to attach to the request. Each header should be specified on a separate line by the string <b>key:value</b> .
	Example: Content-Type : text/plain

Property	Description	
	Note: When using POST, the ap Type:application/octet-stream as default. If you are posting some of JSON or XML, you should add the Type header.	a header by other format, e.g.
Response	The response received from the server is file. This property defines how to handle	-
	Inject as new job: the response is ser data connections as a new job.	nt to the output
	<ul> <li>Attach as dataset: the response is attinput job as an opaque dataset with tin the 'Dataset name' property ('HTTF default) and then the input job is sent connections.</li> </ul>	he name specified 'Response' by
	<ul> <li>Assemble in jobfolder: the response is a new jobfolder together with the inp jobfolder is sent to the output data co jobfolder name is the same as the na (without the extension).</li> </ul>	ut job and the onnections. The
	Discard: the response is discarded. Ir input job is sent to the output data co	
Dataset name	This property is a subordinate property of <b>Response</b> if it is set to <i>Attach as dataset</i> ; it allows you to specify a custom name for the dataset.	
Dataset model	This property subordinate property of <b>Re</b> to <i>Attach as dataset</i> ; it allows you to def model of the response. Options are:	
	Automatic (default). In this case, the of determined by the Content-type key	
	Content-type key	datamodel
	application/json	JSON
	application/xml	XML
	application/vnd.cip4-jdf+xml	JDF
	application/vnd.cip4-jmf+xml	JDF
	anything else	Opaque
	• Opaque	
	• JSON	
	• XML	

Property	Description
	• JDF
File Name	This property is available only if <b>Response</b> is <i>Inject as new job</i> or <i>Assemble in jobfolder</i> .
	The file name (with an extension) to use for the response file.
	Automatic: The file name is taken from the Content-Disposition header of the server response. If the Content-Disposition header is missing or does not contain a valid file name, the extension is taken from the response Content-type and the file name will become [JobNameProper].extension.
Input job	This property is available only if <b>Response</b> is <i>Inject as new job</i> .
	Defines what to do with the input job in case the response file is injected as a new job:
	<ul> <li>Send to output: the input job is sent to the output data connections as a separate job. In other words, the input job and the response file are now two separate jobs.</li> </ul>
	<ul> <li>Attach as dataset: if the input job is a file, it is attached as an opaque dataset with the name specified in the 'Dataset name' property ('HTTPInput' by default) to the new job representing the response file. If the input job is a folder then it is discarded and an error message is logged.</li> </ul>
	Note: If "Attach as dataset" is chosen, you'll get two extra subordinate properties: Dataset name, allowing you to specify a custom name for the dataset, and Dataset model, allowing you to specify the dataset model of the response.
	Discard: the input job is discarded.
Response headers	This property defines how to handle the response headers:
	Attach as dataset: The response headers are saved to a text file (each header on a separate line in format 'key:value') and the file is attached to the output job as an opaque dataset with the name specified in the 'Dataset name' property ('HTTPResponseHeaders' by default) and the dataset model specified in the 'Dataset model' property (JSON (default) or XML).   Discard: The response headers are discarded.
	Discard: The response headers are discarded.

Property	Description
Dataset name	This property is a subordinate property of <b>Response headers</b> if it is set to <i>Attach as dataset</i> ; it allows to specify a custom name for the dataset.
Dataset model	This property is a subordinate property of <b>Response headers</b> if it is set to <i>Attach as dataset</i> ; it defines the response headers dataset model with options JSON(default) and XML.
Retry after failed connection	If enabled, Switch will try again to process jobs that failed due to a network connection failure. This way, you don't have to restart your flow manually.
Retry count	This property is available only if <b>Retry after failed connection</b> is set to <i>Yes</i> .
	The number of retry attempts in case of a network connection error. The default value is 0 (= unlimited retries), meaning that Switch will keep on trying.
Retry delay	This property is available only if <b>Retry after failed connection</b> is set to <i>Yes</i> .
	The delay (in minutes) between each retry attempt. The default value is 10.
Ignore server certificate errors	If set to Yes, server certificate errors will be ignored when connecting to an HTTPS server.
	Examples of certificate errors:
	Self-signed certificate
	Invalid host name
	Expired certificate