# **Impostrip Redirection Integration v1.00**

# Description

The **Impostrip Redirection Integration app** allows you to use the complete functionality offered by the free of charge XML Redirection interface of Ultimates Impostrip Automation and Scalable. This improves the flexibility and allows individual settings on per job base. It also allows the installation of Impostrip on a different machine than the Switch Server and is localized in English and German.

The advantages of this app compared to the build-in-version are, that the following parameters can be controlled directly from within your flow:

- handing over custom values to Impostrip
- defining the page range of the submitted PDF
- changing the page size, the gutters and the margins
- adding blank pages
- adding a LayoutID
- adding an additional mark or barcode

### Compatibility

Switch 13 update 1 and higher.

## **Compatibility third-party applications**

Ultimate Impostrip Automation, Ultimate Impostrip Scalable

#### **Application discovery details**

Impostrip Redirection Integration communicates with Impostrip over the folder architecture of Impostrip. The Impostrip root folder can be selected within the app. The screenshots show the properties, the XML setup in Impostrip and the necessary folder architecture.

This folder architecture can reside in the application folder, where most of the folders already exist (this is the best place to start) or can be moved to any other place afterwards (make sure to modify the folder paths in Impostrip as well).


Name	80	S D Properties	
Name	Property	Value	
AuditFiles	Name	Impostrip Redirection Integration	
	Description		
Hotfolders	Switch Working Path	/Volumes/ImpoStrip	
b in the state state state	Impostrip Working Path	C:\Program Files (x86)\Ultimate Techno.	
ImpoMarks	Impostrip Version	Impostrip Automation	
Input	Timeout waiting time (sec)	600	
P input	Waiting time (sec)	1	
Layouts	Units	mm	
	Hotfolder	Autoflow	
Output	Quantity	1	
Xmlinput	Output all pages	Yes	
	Custom values	Yes	

🧐 XML Configurator	×			
✓ Enable XML Ticket Input Folder				
XML Ticket Input Folder: C:\Users\fkaes\Documents\ImpoStrip Working K	Browse			
Using First File Name as Output Name for XML Redirection Job				
☐ Merge All <printjob> in XML Redirection job into 1 Output File (PDF only)</printjob>				
Use <printcopies> in XML Redirection to generate unique barcodes</printcopies>				
Delete Input Documents and Job File When Job is Done				
Generate Audit XML file for Every Hot Folder Job				
Audit Output Folder: C:\Users\fkaes\Documents\ImpoStrip Working K	Browse			
LaycrImp JDF Input Folder:	Browse			
LayerImp Output Folder: C:\Program Files (x86)\Ultimate Technographics\	Browse			
Use PDF TrimBox to Center Pages				
Search referenced files in this folder:				
Repository File:	Browse			
Universal Xml/Jdf Mapper	Cancel			

# Connections

Impostrip Redirection Integration uses TrafficLight outgoing connections. The processed job is routed according to its status (Success or Error). The created Audit-XML file is routed via the log connection.

The following screen shot demonstrates how the Impostrip Redirection Integration app can be integrated in a Switch flow.



# **Properties detailed info**

80	Properties
Property	Value
Name	Impostrip Redirection Integration
Description	
Switch Working Path	/Volumes/ImpoStrip Working
Impostrip Working Path	C:\Program Files (x86)\Ultimate Techno
Impostrip Version	Impostrip Automation
Timeout waiting time (sec)	600
Waiting time (sec)	1
Units	mm
Hotfolder	Autoflow
Quantity	1
Output all pages	Yes
Custom values	No
Expert Settings	No

## Flow elements properties

- Switch working path:
  - o Path to the Impostrip root folder seen from the Switch Server
- Impostrip working path:
  - Path to the Impostrip root folder seen from Impostrip
- Impostrip version:
  - Used Version of Impostrip (Automation or Scalable)
- Timeout waiting time:
  - o Time the app waits for the imposed job before a timeout occured
- Waiting time:
  - Time Impostrip waits before starting to process the job
- Units:
  - o Units used in the app
- Hotfolder:
  - o the name of hotfolder (setup) used to impose the job
- Quantity:
  - Number of impositions of the job file. When multiple PDFs are handed over in a folder differing numbers of copies can be set for each single PDF by

adding #<*number of copies*> as a suffix to the *NameProper*. Jobs without this suffix will use the "Quantity" value.

E.g. the quantity value is set to "5", two files in a folder are handed over with the jobnames <code>myFirstJob\_#100.pdf</code> and <code>mySecondJob.pdf</code>. This will result in imposing *myFirstJob* a hundred times and *mySecondJob* five times.

- Output all pages:
  - o Output all pages or a given page range
- Custom values:
  - hands over variable data for barcodes and text elements to Impostrip.
    Syntax used for this is <variable defined in Impostrip>TAB<value>CR, e.g.

myJobname	[job.getNameProper]
myJobnumber	12-3456

#### • Expert settings:

Additional settings to overwrite the setup defined in the hotfolder

Expert Settings	Yes
Change Trim page size	Yes
Width	210
Height	297
Show Layout ID	Yes
Comment	Here is a comment
Offset X	0
Offset Y	0
Font Size	12
Change Gutters	Yes
Column	Multi-line text with variables defined
Row	Multi-line text with variables defined
Change Margins	Yes, Custom Paper Size
Right	20
Bottom	10
Add Blank Pages	Yes
Amount	Single-line text with variables defined
Grayscale	50
Caption	Script expression defined
Add Custom Mark	Yes
Name	DynaBC.xml
Target	Paper
Anchor	1 Lower Left
Anchor	4 Bottom left
Offset X	20
Offset Y	20
Rotation	0
All Sheets	Yes
Side(s)	Front